

Resize VM Disk

Resizing the guest disk

General considerations

When you resize the disk of a VM, to avoid confusion and disasters think of the process like adding or removing a disk platter.

If you **enlarge** the hard disk, once you have added the disk plate, your partition table, and file system knows nothing about the new size, so you have to act inside the VM to fix it.

If you **reduce** (shrink) the hard disk, of course removing the last disk plate will probably **destroy** your file system and remove the data in it! So in this case it is paramount to act in the VM in **advance**, reducing the file system and the partition size. SystemRescueCD comes in very handy for it, just add its iso as cdrom of your VM and set boot priority to CD-ROM.

Shrinking disks is not supported by the PVE API and has to be done manually.

Another page (deleted) with overlapping content was [Resizing disks](#) | [Archive](#)

qm command

You can resize your disks online or offline with command line:

```
qm resize <vmid> <disk> <size>
```

exemple: to add 5G to your virtio0 disk on vmid100:

```
qm resize 100 virtio0 +5G
```

For virtio disks:

Linux should see the new size online without reboot with kernel ≥ 3.6

Windows should see the new size online without reboot with last virtio drivers.

for virtio-iscsi disk:

Linux should see the new size online without reboot with kernel ≥ 3.7

Windows should see the new size online without reboot with last virtio drivers.

Enlarge the partition(s) in the virtual disk

Depending on the installed guest there is several different ways to resize the partitions

Offline for all guests

Use **gparted** or similar tool (recommended)

In gparted and possibly most other tools, **LVM and Windows dynamic disc is not supported**

Boot the virtual machine with gparted or similar tool, enlarge the partition and optionally the file system. With some Linux clients you often need to enlarge the extended partition, move the swap partition, shrink the extended partition and enlarge the root partition. (or simply delete the swap partition and create it again - but remember to activate the swap again (last step). Gparted has some warnings about some specific operations not well supported with Windows guest - outside the scope of this document but read the warnings in gparted.

Online for Windows Guests

- Guest is Windows 7, Windows Vista or Windows Server 2008
- Logon as administrator and extend the disk and filesystem (Using Disk manager)
- For more info www.petri.co.il/extend-disk-partition-vista-windows-server-2008.htm
- Guest is Windows 10: logon as administrator and extend the disk and filesystem (Using Disk manager). If you do not see the ability to extend the disk (i.e. nothing seems to have happened as a result of using the resize command), go to the Windows command prompt and do `shutdown -s -t 0` (This is a "normal" shutdown, as opposed to the "fast" shutdown that's the default for Win 8 and onwards.) After a reboot, you'll now see the ability to expand the disk.

Online for Linux Guests

Here we will enlarge a LVM PV partition, but the procedure is the same for every kind of partitions. Note that the partition you want to enlarge should be at the end of the disk. If you want to enlarge a partition which is anywhere on the disk, use the offline method.

- Check that the kernel has detected the change of the hard drive size

(here we use VirtIO so the hard drive is named vda)

```
dmesg | grep vda
```

```
[ 3982.979046] vda: detected capacity change from 34359738368 to 171798691840
```

Print the current partition table

```
fdisk -l /dev/vda | grep ^/dev
```

```
GPT PMBR size mismatch (67108863 != 335544319) will be corrected by w(rite).
```

```
/dev/vda1   34   2047   2014 1007K BIOS boot
```

```
/dev/vda2  2048  262143  260096 127M EFI System
```

```
/dev/vda3 262144 67108830 66846687 31.9G Linux LVM
```

Resize partition 3 (LVM PV) to occupy the whole remaining space of the hard drive)

```
parted /dev/vda
```

```
(parted) print
```

```
Warning: Not all of the space available to /dev/vda appears to be used, you can  
fix the GPT to use all of the space (an extra 268435456 blocks) or continue  
with the current setting?
```

```
Fix/Ignore? F
```

```
(parted) resizepart 3 100%
```

```
(parted) quit
```

Check the new partition table

```
fdisk -l /dev/vda | grep ^/dev
```

```
/dev/vda1   34   2047   2014 1007K BIOS boot
```

```
/dev/vda2  2048  262143  260096 127M EFI System
```

```
/dev/vda3 262144 335544286 335282143 159.9G Linux LVM
```

Enlarge the filesystem(s) in the partitions on the virtual disk

Online for Linux guests with LVM

Enlarge the physical volume to occupy the whole available space in the partition:

```
pvresize /dev/vda3
```

Enlarge the logical volume and the filesystem (the file system can be mounted, works with ext4 and xfs)

```
lvresize --size +20G --resizefs /dev/xxxx/root #This command will increase the partition up by 20GB
```

```
lvresize --extents +100%FREE --resizefs /dev/xxxx/root #Use all the remaining space on the volume group
```

Online for Linux guests without LVM

Enlarge the filesystem (in this case root is on vda1)

```
resize2fs /dev/vda1
```

Revision #1

Created 7 June 2023 00:23:32 by Kory

Updated 7 June 2023 00:28:46 by Kory